


FINE CHINA

Designed by Darlene Zimmerman
www.feedsacklady.com

Featuring **KONA**[®] 2021 COLOR
cotton solids OF THE
YEAR



Finished quilt measures: 56" x 71"





Difficulty Rating: **Advanced**

ROBERT KAUFMAN
F A B R I C S

For questions about this pattern, please email Patterns@RobertKaufman.com.

Fabric and Supplies Needed

Fabric amounts based on yardage that is 42" wide.

Color	Fabric	Name/SKU	Yardage	Color	Fabric	Name/SKU	Yardage
	A	K001-1914 HORIZON	2-1/8 yards		C	K001-1387 WHITE	2-1/8 yard
	B	K001-1514 ROBIN EGG	7/8 yard		Binding*	K001-1914 HORIZON <i>*Also used for Fabric A</i>	5/8 yard
<p>Copyright 2020, Robert Kaufman For individual use only - Not for resale</p>				<p>You will also need: 3-1/3 yard for backing Other: Tri Recs tools Half-Square triangle (EZ Quilting)</p>			

Notes Before You Begin

- Read through all of the instructions before beginning.
- All of the seam allowances are 1/4" unless otherwise noted.
- Press seam allowances open unless otherwise noted.
- Width of fabric (WOF) is equal to at least 42" wide.
- Right sides together has been abbreviated to RST.
- Remember to measure twice and cut once!

Cutting Instructions

From Fabric A, cut:

- six 5-1/2" x WOF strips. Subcut:
 - sixty-two Tri triangles
- seven 3-1/2" x WOF strips. Sew together, using diagonal seams, then set aside for the outer borders.
- two 3" x WOF strips. Subcut:
 - forty Half-Square triangles*
- four 2-1/2" x WOF strips. Subcut:
 - ninety-six Half-Square triangles**

From Fabric B, cut:

- two 3" x WOF strips. Subcut:
 - forty Half-Square triangles*
- five 2-1/2" x WOF strips. Set aside for strip piecing.
- three 2-1/2" x WOF strips. Subcut:
 - forty-eight 2-1/2" squares

From Fabric C, cut:

- six 5-1/2" x WOF strips. Subcut:
 - sixty-two pairs of Recs triangles
- four 3" x WOF strips. Subcut:
 - eighty Half-Square triangles*
- four 2-1/2" x WOF strips. Set aside for strip piecing.
- three 2-1/2" x WOF strips. Subcut:
 - forty-eight 2-1/2" squares
- four 2-1/2" x WOF strips. Subcut:
 - ninety-six Half-Square triangles**

*Open and layer the Fabric A and Fabric C strips right sides together and cut the half-square triangles with the triangle tool. Repeat for the Fabric B and Fabric C strips.

** Open and layer the Fabric A and Fabric C strips right sides together and cut half-square triangles with the triangle tool. They will then be ready to chain sew.

From the Binding Fabric, cut:


- seven 2-1/2" x WOF strips

Assemble the Flower Blocks

Step 1 Sew two strip sets of Fabric B - Fabric C - Fabric B. Press toward the Fabric B strips.




Step 2 Cut the strip sets into twenty-four 2-1/2" units.




Step 3 Sew a strip set of Fabric C - Fabric B - Fabric C. Press the seams toward the Fabric B strip. Cut into twelve 2-1/2" units.




Step 4 Assemble twelve Nine-patch blocks. Press as indicated.




Step 5 Assemble all ninety-six triangle-squares. Press toward the Fabric A triangles. Trim off "dog ears".




Step 6 Assemble twenty-four units as shown. Press as shown.




Step 7 Assemble twenty-four units as shown. Press as shown.



Step 8 Sew the Step 6 units to the top and bottom of the Nine-patch blocks. Press as shown. Make twelve.




Step 9 Sew the Step 7 units to the sides of the Step 8 blocks. Make twelve blocks. Press as shown. At this point the blocks should measure 10-1/2" square.




Assemble the Sashing Pieces


Step 1 Sew a Fabric C Recs triangle to the right side of the Tri unit, matching the "magic angle" on the Recs triangle with the corner of the Tri triangle. Press towards the Fabric C triangle. Make sixty-two units.




Step 2 Sew another Fabric C Recs triangle to the left side of the units from Step 1. Press toward the COTY triangle. Make sixty-two units. At this point the Tri-Recs units should measure 5-1/2" square.




Step 3 Sew the Tri-Recs units with points touching. Make thirty-one pairs. Press the seam open.




Step 4 Assemble all the Fabric A and Fabric B triangle-squares. Press the seams as shown



Step 5 Sew two Fabric A triangle squares and two Fabric B triangle squares together to form a cornerstone. Press as shown. Make twenty. At this point the squares should measure 5-1/2" square.



Assemble the Quilt



Step 1 Using the Quilt Assembly Diagram as a guide, sew the cornerstones, the Tri-Recs pairs and the blocks together in rows. Press toward the Tri-Recs pairs.

Step 2 Sew the rows together, matching and pinning seam intersections.

Step 3: Measure the width of the quilt through the center. Cut two top/ bottom border strips to this width. Sew the borders to the top and bottom of the quilt center. Press toward the border. Measure the length of the quilt through the center. Cut two side border strips to this length. Sew the borders to the sides of the quilt center. Press toward the border.

Your quilt top is complete! Baste, quilt, bind and enjoy!

This pattern may be used for personal purposes only and may not be reproduced in any form without the express permission from Robert Kaufman Fabrics. This pattern is not for resale. All patterns, unless otherwise attributed, are © Robert Kaufman Co., Inc. 2005-2020. All rights reserved.